

Databases and java drivers

Below we have compiled a table with list of databases and JDBC drivers and driver classes

When you configure ConfiDoc with databases as sources you need to specify a driver class and connection URL. These are, very often, quite difficult to find in the first place.

 More about step-by-step configuration of Database datasource for ConfiDoc take a look here: [Using ConfiDoc to connect to Database](#)

We have made it easier for you 😊

Also, check the Atlassian website with helpful hints on troubleshooting your database connections: <https://confluence.atlassian.com/doc/troubleshooting-external-database-connections-9906.html>

Driver	Connection string
MySql/ com.mysql.jdbc.Driver	<code>jdbc:mysql:///?user=&password=</code>  For mySQL driver you will need to enable "generateSimpleParameterMetadata" parameter <code>jdbc:mysql://localhost:3306/mydb?generateSimpleParameterMetadata=true</code>
PostgreSQL/ org.postgresql.Driver	<code>jdbc:postgresql:///?user=&password=</code>
IBMDB2/ COM.ibm.db2.jdbc.app. DB2Driver	<code>jdbc:db2:///?user=&password=</code>
MSSQL(MicrosoftDriver)/ com.microsoft.jdbc.sqlserver. SQLServerDriver	<code>jdbc:microsoft:sqlserver://;databaseName=?user=&password=</code>
MSSQL(Weblogic)/ weblogic.jdbc.mssqlserver4. Driver	<code>jdbc:weblogic:mssqlserver4:@:</code>
MSSQL(SprintaDriver)/ com.inet.tds.TdsDriver	<code>jdbc:inetdae::?database=?user=&password=</code>
MicrosoftSQLServer (JT TurboDriver)/ com.ashna.jturbo.driver.Driver	<code>jdbc:JT Turbo:///?user=/password=</code>
Microsoft SQL Server/ com.microsoft.sqlserver.jdbc. SQLServerDriver	<code>jdbc:sqlserver://yourserver.database.windows.net:1433;database=YourDatabase; user=yourusername@yourserver;password=yourpassword;encrypt=true; trustServerCertificate=false;hostNameInCertificate=*.database.windows.net; loginTimeout=30;</code> https://docs.microsoft.com/en-us/sql/connect/jdbc/building-the-connection-url?view=sql-server-2017
Microsoft SQL Server (alternative, newer) / com. microsoft.jdbc.sqlserver.SQLSer verDriver	<code>jdbc:sqlserver://YourServer:Port;databaseName=YourDatabase</code> More details on https://docs.microsoft.com/en-us/sql/connect/jdbc/using-the-jdbc-driver https://docs.microsoft.com/en-us/sql/connect/jdbc/building-the-connection-url?view=sql-server-2017
OracleThin/ oracle.jdbc.driver.OracleDriver	<code>jdbc:oracle:thin:@::</code>
Oracle(OranhoDriver)/ com.inet.pool.PoolDriver	<code>jdbc:inetpool:inetora:?database=&user=&password=&sid=</code>

Sybase(jConnect5.2)/ ncom.sybase.jdbc2.jdbc. SybDriver	<code>jdbc:sybase:Tds::?user=&password=</code>
PointBaseEmbeddedServer/ com.pointbase.jdbc. jdbcUniversalDriver	<code>jdbc:pointbase://embedded/?user=&password=</code>
Cloudscape/ COM.cloudscape.core. JDBCDriver	<code>jdbc:cloudscape:?user=&password=</code>
CloudscapeRMI/ RmiJdbc.RJDriver	<code>jdbc:rmi:///:/jdbc:cloudscape:?user=&password=</code>
Firebird(JCA-JDBCDriver)/ org.firebirdsql.jdbc.FBDriver	<code>jdbc:firebirdsql:///:?user=&password=</code>
IDSServer/ ids.sql.IDSDriver	<code>jdbc:ids:///:conn?dsn=''</code>
InformixDynamicServer/ com.informix.jdbc.IfxDriver	<code>jdbc:informix-sqli:///:INFORMIXSERVER=</code>
InstantDB/ org.enhydra.instantdb.jdbc. idbDriver	<code>jdbc:idb:</code>
Interbase(InterClientDriver)/ interbase.interclient.Driver	<code>jdbc:interbase:///</code>
HypersonicSQL/ org.hsqldb.jdbcDriver	<code>jdbc:HypersonicSQL:?user=&password=</code>